

Trend Micro™ TippingPoint™ Threat Protection System Release Notes

Version 5.5.6

To ensure that you have the latest versions of product documentation, visit the Online Help Center.

Important notes

This release is supported on 440T and 2200T devices.

- If you are upgrading from an earlier, nonsequential TOS, refer to the release notes of any interim releases for additional enhancements.
- All TPS devices must be running a minimum of v5.4.1 before installing this version. Learn more.
- Use SMS v5.5.4.1 and later to manage a TPS device with this release. SMS v5.5.4.1 upgrades are only supported from an SMS installed with SMS v5.3.0 or later. Attempts to upgrade from an older release will return an error. If the error message is blank, check the SMS system log for the complete message.

Release Contents

Description	Reference
A file handle leak that risked system instability over time has been fixed.	SEG-186133 TIP-94031
SMS file uploads to TPS 440T and 2200T devices no longer fail with a File too big error.	SEG-180383 TIP-93110
A filter override's severity level might not match its updated severity level in the most recent DV package. This mismatch has been fixed.	SEG-151226 TIP-90744
A rare Segmentation fault that could occur in a system with heavy logging has been fixed.	SEG-159644 TIP-85986
A critical failure that could occur while modifying virtual segments on a system under heavy load has been fixed.	SEG-190308 TIP-103051
After an upgrade from TOS v5.4.1, a link-down warning message might be displayed in the system log. This warning can safely be ignored.	TIP-105438
This release fixes a rare segmentation fault involving libdbus and syslog that could cause the device to go into Layer 2 Fallback mode.	TIP-85986 SEG-159644

Product support

For assistance, contact the *Technical Assistance Center (TAC)*.

© Copyright 2023 Trend Micro Incorporated. All rights reserved. Trend Micro, the Trend Micro t-ball logo, TippingPoint, the TippingPoint logo, and Digital Vaccine are trademarks or registered trademarks of Trend Micro Incorporated. All other company and/or product names may be trademarks of their respective owners.