



## Security Management System (SMS) Release Notes

Version 6.6.0.1

This release includes all issues fixed in the *Security Management System Release Notes Version 6.6.0*. For details about those changes, refer to the respective Release Notes on the [Online Help Center](#).

### Important notes for SMS

- All v6.6.0 customers can optionally apply this patch so that the issues it addresses are corrected. However, upgrades to a later TOS do not require an installation of this patch first.
- Patch installation should take approximately 15 minutes.
- To prevent your account from being disabled while you wait for authentication resources to become available after the reboot, navigate to **Edit > Preferences** and make sure that you deselect **Lock user after failed login attempts** and **Auto reconnect client to server after a disconnect occurs**. The SMS automatically reboots after you install this release. You will then be prompted to update the SMS client.
- This patch can be uninstalled or rolled back to the previous version.

## Release contents

The following enhancements or repairs are included in this release.

Description	Reference
An issue where SMS profiles and filter override data no longer appeared in TrendAI Vision One™ after upgrading to SMS 6.6 has been fixed.	PCT-95451
An issue where an sFlow table error appeared in the SMS system log after upgrading from SMS 6.5.1 to 6.6.0 has been fixed.	PCT-93997
An issue where a database migration error caused dashboard panels to appear empty after upgrading to SMS 6.6.0 has been fixed.	PCT-94507
An issue where a database migration error occurred during the upgrade from SMS 6.5.0 to 6.6.0 due to timezone data in the event history has been fixed.	PCT-94774
An issue where reports failed to generate after upgrading to SMS 6.6 has been fixed.	PCT-96255
An issue where SMS database backups could not be saved to an SMB share with SMBv3 encryption enabled has been fixed.	PCT-70187
An issue where custom segment names did not consistently appear in the segment selection window when distributing a profile has been fixed.	PCT-85104 TIP-237516
An issue where client software installers could not be downloaded from the SMS server has been fixed.	TIP-252498
An issue where the SMS database cleanup process remained in a pending state and did not complete without manual intervention has been fixed.	PCT-78669
An issue where Digital Vaccine Toolkit filter names were corrupted after importing multiple packages, causing filters to not appear in search results, has been fixed.	PCT-80829
An issue where the SMS database storage file grew excessively large, filling the database partition and causing SMS operational errors, has been fixed.	TIP-238565
An issue where TrendAI Vision One™ could not display event logs because of corrupted values in the ALERT table has been fixed.	PCT-83064

## Product support

For questions or technical assistance on any TrendAI™ TippingPoint™ product, please contact the TrendAI™ TippingPoint™ [Technical Assistance Center \(TAC\)](#).

© Copyright 2026 Trend Micro Incorporated. All rights reserved. Trend Micro, the Trend Micro t-ball logo, TippingPoint, the TippingPoint logo, and Digital Vaccine are trademarks or registered trademarks of Trend Micro Incorporated. All other company and/or product names may be trademarks of their respective owners.